

```

c=====
c      History: sode.f
c
c      Driver routine which integrates ODEs defining
c      model for deuteron.
c
c      See class notes and Arfken, Math. Methods for
c      Physicists, 2nd Edition, section 9.1.2
c      for more details.
c=====

      program      deut

      implicit      none

      character*4    cdnm
      parameter      ( cdnm = 'deut' )

      integer         iargc,           indlnb,           i4arg
      real*8          r8arg

      real*8          r8_never
      parameter      ( r8_never = -1.0d-60 )

c-----
c      Order of system.
c-----

      integer         neq
      parameter      ( neq = 2 )

c-----
c      Storage for solution at requested output radii.
c-----

      integer         maxout
      parameter      ( maxout = 10 000 )

      real*8          y0(neq)
      real*8          vxout(maxout), vyout(maxout,neq),
      &                  work(maxout)
      integer         nxout,           ixout,           nxout_succ

```

```

integer          ieq

logical          ltrace
parameter        ( ltrace = .true. )

integer          maxdump
parameter        ( maxdump = 50 )

logical          lsodatrace
parameter        ( lsodatrace = .false. )

logical          ivs_ok

c-----
c      LSODA Variables.
c-----

external         fcn,          jac

real*8           y(neq)
real*8           tbgn,         tend
integer          itol
real*8           rtol,         atol
integer          itask,         istate,       iopt
integer          lrw

parameter        ( lrw = 22 + neq * 16 )
real*8           rwork(lrw)

integer          liw
parameter        ( liw = 20 + neq )
integer          iwork(liw)
integer          jt

real*8           tol
real*8           default_tol
parameter        ( default_tol = 1.0d-8 )

c-----
c      Common communication with routine 'fcn' in 'fcn.f' ...
c-----

```

```

include      'fcn.inc'

c-----
c      Parse command line arguments. Deviation from
c      'sode'. Usage is
c
c      deut <x0> <E> [<tol>]
c-----
if( iargc() .lt. 3 ) go to 900

x0      = r8arg(1,r8_never)
E       = r8arg(2,r8_never)
tol     = r8arg(3,default_tol)
if( x0 .eq. r8_never .or. E .eq. r8_never )
&     go to 900

c-----
c      Both boundary conditions are fixed in this case.
c-----
y0(1) = 0.0d0
y0(2) = 1.0d0

c-----
c      Echo command line arguments if "local tracing"
c      enabled ...
c-----
if( ltrace ) then
    write(0,*) 'x0: ', x0
    write(0,*) 'E: ', E
    write(0,*) 'tol: ', tol
end if

c-----
c      Get output radii from standard input ...
c-----
call dvfrom(' - ',vxout,nxout,maxout)
if( nxout .le. 0 ) then
    write(0,*)
    write(0,*) cdnm//': No output radii read from standard input'
    write(0,*) cdnm//': Use (e.g.) dvmesh or dvgmesh to '//
```

```

&           'generate output radii.'
write(0,*)
write(0,*) cdnm//': Sample usages:'
write(0,*)
write(0,*) cdnm//': dvmesh 0.0 1.0 101'
write(0,*) cdnm//': dvgmesh 0.0 1.0 101 10'
write(0,*)
stop
end if
if( ltrace ) then
  if( nxout .le. maxdump ) then
    call dvdump(vxout,nxout,cdnm//': output radii',0)
  else
    call dvdmp1(vxout,work,
&                           int(1.0d0 * nxout / maxdump + 0.5d0),
&                           nxout,cdnm//': selected output radii',0)
  end if
  write(0,*)
  write(0,*) cdnm//': Initial time: ', vxout(1)
  write(0,*)
end if

```

```

c-----
c      Set LSODA parameters ...
c-----

```

```

itol    = 1
rtol    = tol
atol    = tol
itask   = 1
iopt    = 0
jt      = 2

```

```

c-----
c      Initialize the solution ...
c-----

```

```

do ieq = 1 , neq
  y(ieq)      = y0(ieq)
  vyout(1,ieq) = y0(ieq)
end do

```

```

c-----
c      Do the integration ...
c-----
do ixout = 2 , nxout
  istate = 1
c-----
c      Need these temporaries since lsoda overwrites
c      tend ...
c-----
tbgn = vxout(ixout-1)
tend = vxout(ixout)
call lsoda(fcn,neq,y,tbgn,tend,
&           itol,rtol,atol,itask,
&           istate,iopt,rwork,lrw,iwork,liw,jac,jt)
if( lsodatrace ) then
  write(0,1000) cdnm, ixout, nxout, vxout(ixout),
& vxout(ixout+1)
1000  format(' ',a,': Step ',i4,' t = ',1pe10.3,
& ' .. ',1pe10.3)
  write(0,*) cdnm//': lsoda reurns ', istate
end if

if( istate .lt. 0 ) then
  write(0,1500) cdnm, istate, ixout, nxout,
&                 vxout(ixout-1), vxout(ixout)
1500  format(/' ',a,': Error return ',i2,
&                 ' from integrator LSODA./'
&                 '       At output time ',i5,' of ',i5/
&                 '       Interval ',1pe11.3,' .. ',
&                 1pe11.3/)
  nxout_succ = ixout - 1
  go to 500
end if
do ieq = 1 , neq
  vyout(ixout,ieq) = y(ieq)
end do
end do
nxout_succ = nxout

```

```
500    continue

      do ixout = 1 , nxout_succ
        write(*,2000) vxout(ixout),
        &           ( vyout(ixout,ieq) , ieq = 1 , neq )
c-----
c       NOTE: This format will not dump all values on a
c       single line if neq > 10 !!
c-----
2000    format(1P,10E25.16)
      end do

      stop

900    continue
      write(0,*) 'usage: //cdnm//'
      &           ' <x0> <E> [<tol>] '
      write(0,*) ''
      write(0,*) '          Output radii read from standard input'
      stop

      end
```

```

c-----
c      Driver routine which integrates ODEs defining
c      model for deuteron.
c
c      See class notes and Arfken, Math. Methods for
c      Physicists, 2nd Edition, section 9.1.2
c      for more details.
c-----
c      neq = 2
c-----

subroutine fcn(neq,x,y,yprime)
  implicit none

  include    'fcn.inc'

  integer      neq
  real*8       x,        y(neq),     yprime(neq)

  real*8       u,         w

  u = y(1)
  w = y(2)
  yprime(1) = w

  if( x .le. x0 ) then
    yprime(2) = (-1.0d0 - E) * y(1)
  else
    yprime(2) = -E * y(1)
  end if

  return
end

```

```
c-----  
c Application specific common block for communication  
c with derivative evaluating routine 'fcn'.  
c  
c x0: Range of square potential well  
c E: Energy (sought eigenvalue)  
c-----
```

```
real*8  
& x0,  
& E  
common / com_fcn /  
& x0,  
& E
```

```
c-----  
c      Integrates static equations of motion for spherically  
c      symmetric, general-relativistic boson star.  
c  
c      See class notes and Colpi et al, Phys Rev Lett,  
c      vol 57, 2485--2488 for more details  
c-----  
c      neq = 4  
c-----  
  
subroutine fcn(neq,x,y,yprime)  
    implicit none  
  
    include     'fcn.inc'  
  
    integer      neq  
    real*8       x,        y(neq),      yprime(neq)  
  
    real*8       A,        M,        B,        sigma,      xi  
  
    M      = y(1)  
    B      = y(2)  
    sigma = y(3)  
    xi    = y(4)
```

```

if( x .eq. 0.0d0 ) then
    A = 1.0d0
    yprime(1) = 0.0d0
    yprime(2) = 0.0d0
    yprime(3) = 0.0d0
    yprime(4) = ( (Omegasq / B - 1.0d0) * sigma -
&                               Lambda * sigma**3 ) / 3.0d0
else
    A = 1.0d0 / (1.0d0 - 2.0d0 * M / x)
    yprime(1) = x**2 * (
&           0.5d0 * (Omegasq / B + 1.0d0) * sigma**2 +
&           0.25d0 * Lambda * sigma**4 +
&           0.5d0 * xi**2 / A
&           )
    yprime(2) = A * B * x * (
&           (1.0d0 - 1.0d0 / A) / (x**2) +
&           (Omegasq / B - 1.0d0) * sigma**2 -
&           0.5d0 * Lambda * sigma**4 +
&           xi**2 / A
&           )
    yprime(3) = xi
    yprime(4) = xi * (
&           -2.0d0 / x - 0.5d0 * yprime(2) / B +
&           A * (yprime(1) - M / x) / x
&           ) - A * (
&           (Omegasq / B - 1.0d0) * sigma -
&           Lambda * sigma**3      )
end if

return
end

```

```
c-----  
c Application specific common block for communication  
c with derivative evaluating routine 'fcn'.  
c
```

```
c Lambda: Dimensionless phi^4 coupling constant  
c Omega: Eigen-frequency  
c Omegasq: Square of eigen-frequency  
c-----
```

```
real*8  
& Lambda,  
& Omega,  
& Omegasq  
common / com_fcn /  
& Lambda,  
& Omega,  
& Omegasq
```